
Communication protocol

— System instructions



数据接收主机

二、Dongle Description



三、Communication protocol

As shown, the device board calculates the pressure information of the insole through a complex matrix algorithm and transmits it wirelessly to the PC with the receiving dongle.

Note: Sensor devices and receiving dongle are one-on-one use, do not mix. Otherwise, communication will not work properly.

2.4GHz wireless communication USB dongle, PC Device Manager will be enumerated with CH340 serial devices.

Note: Please install the CH340 driver in advance before you can communicate using the dongle.

Baud rate: 115200, 8bit data bit, 1 start ingress bit, 1 termination bit, no check.

Communication mode: single-work communication.

Since the insole matrix is $7x15 \times 105$ size (99 valid data), one sample is transmitted twice, with a total length of one frame of data 61 byte $| (1 \text{ byte len} + 60 \text{ byte load}) |_{\odot}$. The AREA byte domain is distinguished by 'A' 'B'.

Serial frames	LEN	Load					
Bytes	1Byte	2Byte	1Byte	1Byte	56Byte		
Defined	LEN	HEAD	AREA	SeqNo.	Data0		Data55
Description	Data length: Fixed to 2+1+1+56=60 (0x3C)	0xAA 0x55 Represents data Begin	An insole matrix data is transmitted twice; 'A' represents the heel part of the data, 1 to 8 rows, 'B' for the foot part data, 9-15 lines (16th behavior reference voltage);	Sample sequence, full sampling of the entire insole at a time After SeqNo	Y1/Y14, than 7 s suppler Data0/6 and Dat is 'B', Data48 power (1-100)	/Y15 has sensor po mented b 5 is invalid ta41/42/4 as a pero	d when AREA is 'A', 47 none when AREA centage of battery debug information

Reference data frames:

3C AA 55 41 A2 00 FB FC FD FC F7 00 00 FC FC FC FC 00 00 00 F5 FA FB FA 00 00 00 00 00 F8 F9 ED 00 00 00 00 F2 F9 F8 00 00 00 00 00 D9 EF 00 00 00 00 40 D7 00 00 00 00 99 E1

四、Data correspondence for sensors

As shown below, the sensor data is calculated from the heel site to Data0.

